

API Flows Get v3

Contents:

- *Required Permissions*
 - *Request*
 - *Response*
 - *Reference*
-

Retrieve the flow information for a specified flow identifier.

Version: v3

Required Permissions

The authenticated user must be an admin.

i **NOTE:** Each request to the Trifacta® platform must include authentication credentials. See *API Authentication*.

Request

Request Type: GET

Endpoint:

```
/v3/flows/<id>
```

Parameter	Description
<id>	Internal identifier of the flow to retrieve.

Request URI - Example:

```
/v3/flows/10
```

Request Body:

Empty.

Response

Response Status Code - Success: 200 - OK

Response Body Example:

```
[
  {
    "id": 10,
    "name": "2013 POS",
    "description": null,
    "deleted_at": null,
    "cpProject": null,
    "createdAt": "2017-11-07T17:02:34.662Z",
    "updatedAt": "2017-11-07T17:02:34.662Z",
    "createdBy": 1,
    "updatedBy": 1,
    "associatedPeople": [
      {
        "outputHomeDir": "/trifacta/queryResults/admin@trifacta.local",
        "name": "Administrator",
        "email": "admin@trifacta.local",
        "id": 1,
        "flowpermission": {
          "flowId": 3,
          "personId": 1,
          "role": "owner"
        }
      }
    ]
  }
]
```

Reference

Property	Description
id	Internal identifier for the flow
name	Display text for the flow
description	User-friendly description for the flow
cpProject	Not used.
createdAt	Timestamp for when the flow was created
updatedAt	Timestamp for when the flow was last modified
createdBy	Internal identifier of the user who created the flow
updatedBy	Internal identifier of the user who last updated the flow
associatedPeople.outputHomeDir	Output directory for the associated person.
associatedPeople.name	Name of the associated person.
associatedPeople.email	User ID (email address) of the associated person.
associatedPeople.id	Internal ID for the associated person.
associatedPeople.flowpermission.flowId	Internal ID for the flow.
associatedPeople.flowpermission.personId	Internal ID for the permitted user.
associatedPeople.flowpermission.role	Role for the permitted user. <ul style="list-style-type: none"> owner - can do anything to the flow. collaborator - can do most actions on the flow except change the name and delete the flow.

