


Privileges and Roles Reference

Contents:

- *Privileges*
 - *Flows*
 - *Connections*
 - *Plans*
- *Standard Roles*
 - *default*
 - *Workspace admin*

 **Feature Availability:** This feature may not be available in all product editions. For more information on available features, see *Compare Editions*.

In the Designer Cloud® application, you can create and assign roles, each of which consists of one or more privileges. A **privilege** is a level of access to a type of object, such as flows.

Below, you can review the available privileges, including the supported levels for each.

For more information on privileges and roles, see *Overview of Authorization*.


Privileges

Flows

The flows privilege governs access to flow objects.

Access Level	Name	Description
0	none	Assigned role cannot see or use flows, including the pages where flows are available.
1	viewer	Assigned user can access Flows page and Flow View page for flows that the user owns or has been shared. User can also run jobs on the user's own flows. User cannot make changes to any flows.
2	editor	All of the above, plus: Assigned user can edit, share, and run jobs on flows to which the user has access. <div style="border: 1px solid #ccc; padding: 5px; margin: 10px 0;">NOTE: By default, editors can also schedule flows. This option can be disabled by an administrator.</div>
3	author	All of the above, plus: Assigned user can create new flows, schedule flows, and delete flows.


Connections

 **Feature Availability:** This feature may not be available in all product editions. For more information on available features, see *Compare Editions*.

The connections privilege governs access to connection objects.

Access Level	Name	Description
0	none	Assigned role cannot see or use connections, including the pages where connections are available.
1	viewer	Assigned user can access Connections page for connections that the user owns or has been shared. User can share connections. User cannot make changes to any connections.
2	editor	All of the above, plus: Assigned user can edit and share connections to which the user has access.
3	author	All of the above, plus: Assigned user can create new connections and delete connections.

Plans

 **Feature Availability:** This feature may not be available in all product editions. For more information on available features, see *Compare Editions*.

The plans privilege manages access to plan objects.

Access Level	Name	Description
0	none	Assigned role cannot see or use plans, including the pages where plans are available.
1	viewer	Assigned user can access Plans page and Plan View page for plans that the user owns or has been shared. User can also run jobs on the user's own plans. User cannot make changes to any plans.
2	editor	All of the above, plus: Assigned user can edit, share, and run jobs on plans to which the user has access. <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;">NOTE: By default, editors can also schedule plans. This option can be disabled by an administrator.</div>
3	author	All of the above, plus: Assigned user can create new plans, schedule plans, and delete plans.

Standard Roles

The following roles are provided with the product.

NOTE: The following roles cannot be removed.

default

The default role is assigned to each user when the user is initially created. This role contains the following permissions:

Privilege	Access Level/Name
Flows	3 - author
Connections	3 - author
Plans	3 - author
User defined functions	3 - author

Tip: You can modify the default role if you want to set a lower level of base access for each new user of the product. For more information, see *Overview of Authorization*.

Workspace admin

This role provides super-user privileges to the assigned user.

NOTE: This role enables for the user owner-level access to all objects in the project or workspace and access to all admin-level settings and configuration pages in the admin console. This role should not be assigned to many users. At least one user should always have this role.

NOTE: You cannot modify or delete this role.