

Manage Flows with Folders

Contents:

- *Create Folder*
- *Move to Folder*
- *Delete Folder*

Folders allow you to group related flows into a common organizing structure. For example, you can use folders to group flows by project, by source of data, or by other meaningful grouping.

Limitations:

- Each flow in a folder is an independent object. Permissions can vary between flows in a folder and should be reviewed after adding them.
- You can only move flows that you own.
- You cannot share folders or modify permissions at the folder level.
- Folders cannot be exported and imported.

Create Folder

You can create a folder in one of two ways:

- Click the **Create** button. Then, select **Create Folder**. Enter a name and description for the folder. These values appear in the application. Click **Create**.
- When you move a flow, you can optionally create a new folder for it. See below.

Move to Folder

To move a flow to a folder, select **Move** from the context menu on the right side of the screen for the flow.




Figure: Move to Folder dialog

- To move the flow, select the name of the flow. Click **Move**.
- To search folder names, enter your search string in the Search textbox.
- To move the flow into a new folder, click **Create new folder**. Enter a meaningful name and description for the folder. Select **Move to new folder**.

Delete Folder

To delete a folder, select **Delete Folder** from the context menu on the right side of the screen.

This step deletes the folder and all flows within it. This step cannot be undone.